# IPv6 Autoconfiguration

## Stateless and Stateful

Rabat, Maroc
28 - 30 Mars 2007

*Philippe.Bereski@alcatel.fr*

*Simon.Muyal@renater.fr*
*Bernard.Tuy@renater.fr*

Rabat, Maroc –Mars 2007

IPv6 Dissemination and Exploitation

---

# Copy ... Rights

- This slide set is the ownership of the 6DISS project via its partners

- The Powerpoint version of this material may be reused and modified only with written authorization

- Using part of this material must mention 6DISS courtesy

- PDF files are available from *www.6diss.org*

- Looking for a contact ?
- Mail to : martin.potts@martel-consulting.ch
- Or bernard.tuy@renater.fr

Rabat, Maroc –Mars 2007

IPv6 Dissemination and Exploitation

# Contributions

- Main authors
  - Miguel Baptista, FCCN, Portugal
  - Carlos Friaças, FCCN, Portugal
- Contributors
  - Mónica Domingues, FCCN, Portugal
  - Paulo Ferreira, FCCN, Portugal
  - Bernard Tuy, Renater, France

IPv6 Dissemination and Exploitation

---

# Prerequisites

- You must have followed previously the modules:
  - 010-IPv6 Introduction
  - 020-IPv6 Protocol
  - 030-IPv6 Addressing
  - 040-IPv6 Associated Protocols

IPv6 Dissemination and Exploitation

# Agenda

- Stateless Autoconfiguration
- Stateful Autoconfiguration (DHCPv6)
- Conclusions

# Stateless Autoconfiguration

- Hosts should be plug & play
- Uses some of the Neighbor Discovery ICMPv6 messages
- When booting, the host asks for network parameters:
  - IPv6 prefix(es)
  - default router address(es)
  - hop limit
  - (link local) MTU

# Stateless Autoconfiguration

- Only routers have to be manually configured
  - but work on prefix delegation is in progress
    *(http://www.ietf.org/rfc/rfc3633.txt)*

- Hosts can get automatically an IPv6 address
  - BUT it isn't automatically registered in the DNS

- but servers should be manually configured

---

# Stateless Autoconfiguration

- IPv6 Stateless Address Autoconfiguration is described in RFC 2462

- Hosts are listening for Router Advertisements (RA) messages, periodically transmited by routers

- RA messages coming from the router(s) on the link identify the subnet

- Allows a host to create a global IPv6 address from:
  - Its interface identifier (EUI-64 address)
  - Link Prefix (obtained via Router Advertisement)
- Global Address = combine *Link Prefix* with *EUI-64 address*

# Stateless Autoconfiguration

- Usually, the router sending the RA messages is used, by hosts, as the default router
- If the RA doesn't carry any prefix
  - The hosts don't configure (automatically) any global IPv6 address (but may configure the default gateway address)
- RA messages contain two flags indicating what type of stateful autoconfiguration (if any) should be performed
- It's impossible to automatically send DNS server addresses
- IPv6 addresses depends on NIC card

# Stateless Autoconfiguration example



MAC address is 00:0E:0C:31:C8:1F

EUI-64 address is 20E:0CFF:FE31:C81F

Internet

FE80::20E:0CFF:FE31:C81F

2001:690:1:1:20E:0CFF:FE31:C81F

Router Solicitation
Dest. FF02::2

::/0          FE80::20F:23FF:FEf0:551A

FF02::2 (All routers)
FE80::20F:23FF:FEf0:551A
2001:690:1:1

5

# Stateful autoconfiguration
## (DHCPv6)

- Dynamic Host Configuration Protocol for IPv6
  - RFC 3315
  - stateful counterpart to IPv6 Stateless Address Autoconfiguration.
- According to RFC3315 DHCPv6 is used when:
  - no router is found
  - Or if Router advertisement message enable use of DHCP

IPv6 Dissemination and Exploitation

---

# Stateful autoconfiguration
## (DHCPv6)

- DHCPv6 works in a client-server model
  - Server
    - Responds to requests from clients
    - Optionally provides the client with:
      - IPv6 addresses
      - Other configuration parameters (DNS servers…)
    - Is listening on multicast addresses:
      - All_DHCP_Relay_Agents_and_Servers (FF02::1:2)
      - All_DHCP_Servers (FF05::1:3)
    - Memorize client's state
    - Provide means for securing access control to network resources

IPv6 Dissemination and Exploitation

# Stateful autoconfiguration
## (DHCPv6)

- Client
  - initiates requests on a link to obtain configuration parameters
  - use its link local address to connect the server
  - Send requests to FF02::1:2 multicast address (All_DHCP_Relay_Agents_and_Servers)
- Relay agent
  - node that acts as an intermediary to deliver DHCP messages between clients and servers
  - is on the same link as the client
  - Is listening on multicast addresses:
    - All_DHCP_Relay_Agents_and_Servers (FF02::1:2)

---

# Stateful Autoconfiguration example

Internet

Example: in /etc/resolver.conf file

Information-Request
(DNS Server's address?)

DHCPv6 Server
FF02::1:2
(All_DHCP_Relay_Agents_and_Servers)

Reply-message
DNS 2001:690:5:0::10

# Conclusions

- The two types of configuration complement each other
  - Example: we can obtain the address from stateless autoconfiguration and the DNS server address from DHCPv6

- In dual-stack networks we can obtain DNS server addresses from **DHCPv4**

- DHCPv6 clients still aren't available in Operating Systems.
  - So, we still need to run a client
  - No transparent to users

IPv6 DNS Examination and Exploitation

# Questions?

IPv6 DNS Examination and Exploitation