IPv6 Autoconfiguration

Stateless and Stateful

Miguel Baptista – miguel.baptista@fccn.pt

Copy ... Rights

- This slide set is the ownership of the 6DISS project via its partners

- The Powerpoint version of this material may be reused and modified only with written authorization

- Using part of this material must mention 6DISS courtesy

- PDF files are available from *www.6diss.org*

- Looking for a contact ?
- Mail to : martin.potts@martel-consulting.ch
- Or bernard.tuy@renater.fr

Contributions

- Main authors
  - Miguel Baptista, FCCN, Portugal
  - Carlos Friaças, FCCN, Portugal
- Contributors
  - Mónica Domingues, FCCN, Portugal
  - Paulo Ferreira, FCCN, Portugal
  - Bernard Tuy, Renater, France
  - Pedro Lorga, FCCN, Portugal

Prerequisites

- You must have followed previously the modules:
  - 010-IPv6 Introduction
  - 020-IPv6 Protocol
  - 030-IPv6 Addressing
  - 040-IPv6 Associated Protocols

Agenda

- Stateless Autoconfiguration

- Stateful Autoconfiguration (DHCPv6)

- Conclusions

Stateless Autoconfiguration

- Hosts should be plug & play

- Uses some of the Neighbor Discovery ICMPv6 messages

- When booting, the host asks for network parameters:
  - IPv6 prefix(es)
  - default router address(es)
  - hop limit
  - (link local) MTU

Stateless Autoconfiguration

- Only routers have to be manually configured
  - but work on prefix delegation is in progress

    [http://www.ietf.org/rfc/rfc3633.txt]

- Hosts can get automatically an IPv6 address
  - BUT it isn't automatically registered in the DNS

- but servers should be manually configured

Stateless Autoconfiguration

- IPv6 Stateless Address Autoconfiguration is described in RFC 2462

- Hosts are listening for Router Advertisements (RA) messages, periodically transmited by routers

- RA messages coming from the router(s) on the link identify the subnet

- Allows a host to create a global IPv6 address from:
    - Its interface identifier (EUI-64 address)
    - Link Prefix (obtained via Router Advertisement)
- Global Address = combine *Link Prefix* with *EUI-64 address*

Stateless Autoconfiguration

- Usually, the router sending the RA messages is used, by hosts, as the default router

- If the RA doesn't carry any prefix
  - The hosts don't configure (automatically) any global IPv6 address (but may configure the default gateway address)

- RA messages contain two flags indicating what type of stateful autoconfiguration (if any) should be performed

- It's impossible to automatically send DNS server addresses

- IPv6 addresses depends on NIC card

Stateless Autoconfiguration example

Internet

MAC address is 00:0E:0C:31:C8:1F

EUI-64 address is 20E:0CFF:FE31:C81F

2AD1the1EpN0CSA0:FE31C81FDu1DND
Do the Link-Local Address is chosen

FE80::20E:0CFF:FE31:C81F

2001:690:1:1:20E:0CFF:FE31:C81F

Router Solicitation
Dest. FF02::2

*/0   FE80::20F:23FF:FEf0:551A

FF02::2 (All routers)
Router Advertisement
FE80::20F:23FF:FEF0:551A
2001:690:1:1

Stateful autoconfiguration (DHCPv6)

- ## Dynamic Host Configuration Protocol for IPv6

  - RFC 3315

  - stateful counterpart to IPv6 Stateless Address Autoconfiguration.

- ## According to RFC3315 DHCPv6 is used when:

  - no router is found

  - Or if Router advertisement message enable use of DHCP

Stateful autoconfiguration (DHCPv6)

- **DHCPv6 works in a client-server model**
  - Server
    - Responds to requests from clients
    - Optionally provides the client with:
      - IPv6 addresses
      - Other configuration parameters (DNS servers...)
    - Is listening on multicast addresses:
      - All_DHCP_Relay_Agents_and_Servers (FF02::1:2)
      - All_DHCP_Servers (FF05::1:3)
    - Memorize client's state
    - Provide means for securing access control to network resources

Stateful autoconfiguration (DHCPv6)

- Client
  - initiates requests on a link to obtain configuration parameters
  - use its link local address to connect the server
  - Send requests to FF02::1:2 multicast address (All_DHCP_Relay_Agents_and_Servers)
- Relay agent
  - node that acts as an intermediary to deliver DHCP messages between clients and servers
  - is on the same link as the client
  - Is listening on multicast addresses:
    - All_DHCP_Relay_Agents_and_Servers (FF02::1:2)

Stateful Autoconfiguration example

3. Client updates configuration after Reply message
2. Server responds with a Reply message

Example: in /etc/resolver.conf file

Internet

DHCPv6 Server
FF02::1:2
(All_DHCP_Relay_Agents_and_Servers)

Information-Request
(DNS Server's address?)

Reply-message
DNS 2001:690:5:0::10

Conclusions

- The two types of configuration complement each other
  - Example: we can obtain the address from stateless autoconfiguration and the DNS server address from DHCPv6

- In dual-stack networks we can obtain DNS server addresses from **DHCPv4**

- DHCPv6 clients still aren't available in Operating Systems.
  - So, we still need to run a client
  - No transparent to users

Questions?